

# CRITERION GOES TO THE MOVIES

---

USER'S GUIDE  
FOR MACINTOSH

## **VOYAGER**

578 Broadway  
Suite 406  
New York, NY 10012

QT06

## **TECHNICAL REQUIREMENTS**

- Any color Macintosh (25-MHz 68030 or better recommended)
- 3,500K of available RAM
- 13-inch (640×480 resolution) or greater color monitor
- QuickTime™-compatible CD-ROM drive (double-speed recommended)
- System 7

## **REGISTRATION AND SOFTWARE SUPPORT**

Please fill out and return the enclosed warranty card. This registers your copy of the software and entitles you to telephone support. Call (914) 591-5500 for software support.

## **SETTING UP**

Before you can use this software, you must:

- Make sure that your CD-ROM drive's special software is installed
- Install the QuickTime extension from the CD if necessary
- Copy HyperCard 2.1 from the CD to your hard drive if necessary
- Allocate 3,500K of memory to HyperCard if necessary
- Install the necessary fonts from the CD
- Copy "Criterion's Movies" from the CD to your hard drive

### **Installing Your CD-ROM Drive's Special Software**

If you've never used your CD-ROM drive before, you must install its software. This software should be on the floppy disk that came with your drive. Please see the manufacturer's instructions if necessary.

## Installing Software from the CD

1. Insert the CD into your CD-ROM drive according to the drive manufacturer's instructions.
2. Double-click the CD's icon. A window showing its contents will open.

Everything you may need to install appears in this window. Keep it open until you're finished setting up.

## Installing the QuickTime Extension

If the QuickTime (1.6.1 or later) extension isn't already installed on your Macintosh, follow these steps:

1. Drag the QuickTime™ icon to the System Folder icon on your hard drive and drop it. Your Macintosh will guide you through the rest of the QuickTime installation.
2. Restart your Macintosh.
3. Re-insert the CD and open it again to proceed with the installation.

## Installing HyperCard

If HyperCard 2.1 isn't already on your hard drive, drag the HyperCard 2.1 folder to your hard drive to install it.

## Allocating Memory to HyperCard

If you have copied HyperCard from the CD, you can skip this step because the copy provided has the correct memory settings. Otherwise, you need to allocate 3,500K of memory to HyperCard as follows:

1. Locate your copy of HyperCard on the hard drive and select it.
2. Choose Get Info from the File menu. A HyperCard Info window will appear.
3. Enter "3500" in the box at the lower-right corner of the HyperCard Info window.
4. Close the HyperCard Info window.

## Installing Fonts

For text to display correctly, you must install the fonts provided on the CD as follows:

1. Drag the CGTTM Fonts suitcase over the System Folder icon on your hard drive and drop it. Your Macintosh will guide you through the rest of the font installation.

If you use HyperCard regularly, you can skip steps 2 and 3, because you have almost certainly installed the HyperCard fonts already. If not, proceed as follows:

2. Locate the HyperCard folder on your hard drive and double-click to show its contents.
3. Drag the HyperCard Fonts suitcase over the System Folder icon on your hard drive and drop it. Your Macintosh will guide you through the rest of the font installation.

## Copying "Criterion's Movies"

Drag "Criterion's Movies" to your hard drive to copy it.

## LAUNCHING *CRITERION GOES TO THE MOVIES*

Every time you wish to use *Criterion Goes to the Movies*, make sure that the CD is in your CD-ROM drive, and that its icon appears on your desktop. Double-click the copy of "Criterion's Movies" on your hard drive to start.

If you encounter problems at this point, it may be because you have an extra copy of HyperCard (or HyperCard Player) on your drive. Locate the copy of HyperCard 2.1 whose memory size you set according to the instructions in "Allocating Memory to HyperCard" above. Drag the "Criterion's Movies" icon directly to this copy and drop it when HyperCard is highlighted.

## **COPYRIGHT INFORMATION**

The images and clips contained on the CD-ROM are licensed for use solely in *Criterion Goes to the Movies* and may not be copied or used outside of this catalogue without the written permission of the copyright holders. Write to Voyager for copyright information.