

Press on any of the elements waveforms to mute and unmute them.

Mode Selection : Press this to switch to Sampler Mode.

The X's mean some elements are not present in the drumloop: Blue is for Kick, Red is for Snare, Yellow is for HiHat, Green for Percussions.

Selected Drumloop : the slices of this loops will be played according to the selected LoopMorph Preset score.

Preview Original will play the selected drumloop with its corresponding extracted score in Loopmorph Presets.

If autoname is on, Miracle will ask you the export name once, and add automatically increasing numbers after the chosen name, so you can export several variations very fast.

Export created loop in wav file format at host samplerate and at 16bit, one bar or two bars, depending if 'reduce to one bar' is activated or not.

Activate Render when rendering or freezing your in your host (if you use live MIDI input for preset selection)

Bypass Miracle (lets the sound go through in FX version)

Envelope controls.
Right Click to init knob, ALT+click and move to set all knobs of the column
Led for each 4 physical stereo outputs
Reverse : will keep the sample attack transient in time in LoopMorph mode.

Selected LoopMorph Preset : the slices of the drumloop chosen will be played according to this LoopMorph Preset score.

Activates MIDI Input for live preset selection

Adds Shuffle to the loop. 3 positions: off, soft (orange) or hard shuffle (green).

Adds slight rhythmic, and velocity mistakes to humanize the loop.

RMS level will match the LoopMorph preset RMS level of each slices on the sounds of the drumloop.


MIDI keyboard : All slices types are mapped automatically as follows :

- C Kick 1
- C# Kick 2
- D Kick 3
- D# Snare 1
- E Snare 2
- F Snare 3
- F# HiHat 1
- G HiHat 2
- G# HiHat 3
- A Percussion 1
- A# Percussion 2
- B Percussion 3

The advantage is that you can program your own beats in your host, and browse for other drumloops without any effort in terms of MIDI mapping.

SAMPLER MODE

All other controls shown here are the same as in Loopmorph mode.



Mode Selection : Press this to switch back to LoopMorph Mode.

LoopMorph Presets and associated tools hide as you uses your host do creates the beats and grooves.