

Welcome to Music Town!

Thank you for purchasing The Musical World of Professor Piccolo! We hope you enjoy using this interactive, educational overview of many musical topics, especially on the ambitious task of creating an enjoyable course on the basics of music theory.

We hope that The Musical World of Professor Piccolo will serve as a launching point for further study toward a lifetime of enjoyment of this most exciting living language known as music.

–Opcode Interactive

***** IMPORTANT INSTALLATION INFORMATION *****

Installation

You will see two folders on the CD-ROM labeled "Professor Piccolo MIN" and "Professor Piccolo FULL". Drag one of these folders to your hard drive to install the program depending on the amount of hard disk space you have available.

"Professor Piccolo MIN" copies the minimum amount of files needed to run the program. You will need to have at least 4MB free hard disk space to run Professor Piccolo this way.

"Professor Piccolo FULL" copies all of the Professor Piccolo data files from the CD-ROM to your hard drive and requires at least 23MB free hard disk space. Running the program this way offers the best performance.

Running Professor Piccolo

To run the program, simply open the Professor Piccolo folder on your hard drive, and double-click on the icon of the Professor Piccolo application program.

You must have the CD-ROM in the CD-ROM drive to run the program correctly and hear the CD-Audio sounds.

System Setup Information

You will need to have the following System Extensions installed to run the program correctly:

QuickTime 2.0 (or higher)
Apple CD-ROM 5.0 (or higher)
Your printer's driver (e.g. Laserwriter,
Imagewriter, etc.)

These extensions come with your system software. If these extensions are

unavailable to you then re-install your System 7.5 or higher software. Make sure these extensions are active.

Important!

Check these Control Panels and make sure the following are set correctly:

Memory: VIRTUAL MEMORY - OFF

MODERN MEMORY MANAGER - OFF

Monitor: 256 Colors

Sound: Go to "Sound In" and click the "Options" button. Make sure that "Internal

CD" and "Playthrough" are selected. Go to Volumes and make sure your

desired Volume level is set to an audible level.

Gradebook Utility

For teachers and parents, there is a separate application called "Gradebook". This utility will allow you to view all of the current users and what lessons they have completed in the Music School, as well as let you delete user records. To use "Gradebook", simply copy the file from the CD-ROM to your hard drive and double-click on the icon of the application to run it.

Uninstalling Professor Piccolo

To uninstall the program, simply drag the Professor Piccolo folder and the ppPrefs file (located in your System Folder) to the trash and empty the trash.

Troubleshooting

Problem: No sound is heard.

Try This: Turn up the volume using the Sound control panel, or from the volume buttons

on the front of your computer.

Problem: Some sounds play, but others don't.

Try This: Make sure you have the Apple CD-ROM and QuickTime 2.0 extensions installed

You can use the Extensions Manager Control Panel to make sure are selected. Also check the CD-Audio volume level using the

on the

properly.

that these

AppleCD

Audio Player utility application located under the Apple Menu.

Problem: The sounds don't seem to fit the movie.

Try This: Make sure the Professor Piccolo CD is in the CD-ROM drive.

Problem: Printing does not work.

Try This: Turn on Appletalk using the Chooser. Make sure your printer driver shows

up and that it is selected. If it does not, try re-installing your printer driver or system software. Make sure that the printer is on and that it is

connected

properly.

Problem: The wrong pictures are displayed in the Instrument Library.

Try This: Make sure QuickTime 2.0 is installed and active using the Extensions Manager

Control

Panel. Also try re-starting your computer.

Problem: Strange and erratic things are happening.

Try This: Make sure Virtual Memory and Modern Memory Manager are turned OFF. Turn

off all

other extensions besides Apple CD-ROM, QuickTime, and your printer

driver.

If you can't resolve the problem with these troubleshooting tips, call the Opcode

Interactive Technical Support line at 415-494-9393, Monday through Friday, 9am-5pm Pacific Standard Time.

Opcode Interactives's Limited 90 Day Warranty

Except to the extent prohibited by law, all implied warranties made by Opcode Interactive in connection with this manual and software are limited in duration to ninety (90) days from the date of original purchase, and no warranties, whether express or implied, shall apply to this product after said period.

Opcode Interactive makes no warranty or representation, either express or implied, with respect to the software described in this manual. This software is sold "as is". The purchaser assumes the entire risk as to its quality and performance. Under no circumstances shall Opcode Interactive be liable for any loss or damage, direct, consequential, or incidental, arising out of the use or inability to use this product.

Some states do not allow limitations on how long an implied warranty lasts or the exclusion or limitation of incidental or consequential damages, so the above limitations or exclusions may not apply to you.

Copyright

This software and manual are copyrighted ©1995 by Opcode Interactive with all rights reserved. The software or manual may not be copied, in whole or part, without the express written consent of Opcode Interactive.

Unauthorized duplication is prohibited. This software is protected by both United States Copyright Law and International Treaty provisions. If you have any problems with the software, please consult the user's guide or on-line help first. If you still have a problem, call the Opcode Interactive Technical Support line at 415-494-9393, Monday through Friday, 9am-5pm Pacific Standard Time.