Rodney's Wonder Window

MACINTOSH & WINDOWS
USER'S GUIDE

TECHNICAL SUPPORT

Call 212.219.2522 for software support, or send email to any of the following addresses:

Internet: techsupport@voyagerco.com

American Online: voyager@aol.com, or go to the AOL Voyager forum: keyword is "voyager"

CompuServe: 75300,1635 or go to the Multimedia A Vendor forum

---

CityROM, 299 Queen Street West, Toronto, Ontario Canada M5V 2Z5

REGISTRATION AND SOFTWARE SUPPORT

Please register your software for technical support and so that we can keep you posted on the ever-growing Voyager catalog. To register this Voyager title for MAC OS, see the Software Registration file in th Documentation folder on the CD-ROM. For Windows, see the SOFT-REG.TXT file in the REGISTER directory on the CD-ROM.

You can return this information by email or register@voyagerco.com or by fax to 914.591.6481

CONTENTS

TECHNICAL REQUIREMENTS—MACINTOSH

- Any color Macintosh
- System Software 6.0.7 or higher
- 3000K of available memory (at least 4 megabytes of RAM installed)
- 13-inch (640×480 resolution) or greater color monitor
- CD-ROM drive (double-speed recommended)

SETTING UP—MACINTOSH

Before you can use this software, you must:

- Make sure that your CD-ROM drive's special software is installed
- Install the QuickTime™ extension from the CD if necessary
- Copy *Wonder Window* from the CD to your hard drive
- Make sure your monitor is set to display 256 colors

Installing Your CD-ROM Drive's Special Software

If you've never used your CD-ROM drive before, you must install its own special software. This software should be on the floppy disk that came with your drive. Please see the manufacturer's instructions if necessary.

Installing Software from the CD

1. Insert the CD into your CD-ROM drive according to the drive manufacturer's instructions.

2. Double-click the CD's icon. A window showing its contents will open.

Everything you may need to install appears in this window. Keep it open until you're finished setting up.

INSTALLING THE QUICKTIME EXTENSION

If the QuickTime (1.6.1 or later) extension isn't already installed on your Macintosh, proceed as follows:

1. Drag the icon named "QuickTime™" to the System Folder icon on your hard drive and drop it. Your Macintosh will guide you through the rest of the QuickTime installation.

2. Restart your Macintosh.

3. Re-insert the CD and open it again to proceed with the installation.

COPYING *WONDER WINDOW*

Drag the *Wonder Window* icon to your hard drive to copy it.

SETTING YOUR MONITOR

Go to the Monitors control panel (through the Apple Menu) and make sure that your monitor is set to display 256 colors. Close the control panel.

Using *Rodney's Wonder Window*

Every time you want to use *Wonder Window,* you must put the CD into the CD-ROM drive and double-click on the *Wonder Window* icon on your hard drive. Do not try to launch the program directly from the CD.

How to use *Wonder Window?* Half the fun comes from finding out on your own. Just click on things and see what happens!

TECHNICAL REQUIREMENTS—WINDOWS

- PC-compatible computer with a 486SX-25 or higher microprocessor
- 4 MB of memory (8 MB recommended)
- 1.4 MB of hard drive space
- 640×480, 256-color display
- MPC-compatible CD-ROM drive
- MPC-compatible sound card with speakers or headphones
- Mouse
- MS-DOS operating system version 5.0 or later
- Microsoft Windows version 3.1, or version 3.0 with Multimedia Extensions 1.0
- Microsoft MS-DOS CD-ROM Extensions (MSCDEX) version 2.2 or later

SETTING UP—WINDOWS

1. Place the *Rodney's Wonder Window* disc (label side up) in the CD-ROM drive.

2. From within the Windows File Manager, click on the drive icon for your CD-ROM drive to display the disc's files. Double-click on the SETUP.EXE file to run the Setup program. Or, from within the Program Manager, choose Run from the File menu, then type *d:setup.exe,* where *d:* is your CD-ROM drive.

3. In the Setup dialog boxes, verify the drive you are installing from, and the drive and directory into which *Rodney's Wonder Window* will be installed. Type in a new drive or directory, or accept the defaults.

4. When you are done making your selections, click "Continue." The setup program will copy the necessary files to your hard drive, and create a Voyager group in the Program Manager containing the *Rodney's Wonder Window* icon and a ReadMe file.

5. While the files are being installed, you can stop the installation by clicking "Cancel." This will result in an incomplete installation.

GETTING STARTED IN WINDOWS

After you've run the Setup program, you're ready to explore. To start *Rodney's Wonder Window*:

1. Make sure that your CD-ROM drive and speakers or headphones are hooked up, and turn on your computer.

2. Place the *Rodney's Wonder Window* disc (label side up) in the CD-ROM drive and start Windows.

3. Make sure that your video display is set to 256 colors. *Rodney's Wonder Window* is designed to run with 256 colors, however, it will run with just 16 colors. If your display is set to greater than 256 colors, you will be prompted to change to either 256 or 16 colors.

4. If your system only has 4 MB of memory, make sure that at least 2 MB of virtual memory is turned on. You can check to see if virtual memory is turned on by double-clicking on the Control Panel icon within the Main group of Program Manager. Select the 386 Enhanced control panel and click on the Virtual Memory button. This will tell you the status of your virtual memory. If you need to make changes to your virtual memory settings, refer to your Windows manual.

5. Quit any other open applications, except for the Program Manager.

6. From the Program Manager, double-click on the *Rodney's Wonder Window* icon.

7. Do not try to run RWW.EXE directly from the CD-ROM. Performance will suffer when trying to access the program, animation, and sound files at the same time.

8. After the program has launched, the *Rodney's Wonder Window* main menu appears. Choose a window and click its picture. You will be taken to the activity you have chosen.

Copyright © 1992, 1994 Rodney A. Greenblat