



## Macintosh® Reference Card

Crossword Magic comes with the most recent version of the Macintosh® System so it is a self-booting disk. In addition, Laser-Prep, LaserWriter®, and ImageWriter® printer files are included on the program disk. If you are using a different printer and therefore need to use a different printer file, copy one, two, or all three of the files to another disk. Then remove the file(s) from the **Crossword Magic** program disk, and replace them with the printer files that you want to use. (The printer files are included as part of the Macintosh System that came with your computer.)

### Installing Crossword Magic on a Hard Disk

**Crossword Magic** is copy-protected but can be installed once onto a hard drive. To install **Crossword Magic** on your hard disk follow these steps:

1. Turn on the hard disk drive.
2. Turn on the computer and insert the **Crossword Magic** program disk into a floppy drive.
3. Copy the contents of the **Crossword Magic** program disk onto your hard drive by dragging the **CM Disk** icon over your hard drive's icon. A folder called **CM Disk** will be created on your hard drive, and all the **Crossword Magic** files will be copied into it.
4. When the copy process is complete, open the newly created **CM Disk** folder and double-click on the **Crossword Magic** program icon. A dialog box will appear. It will tell you how many hard disk installs remain on the disk (it should be 1) and give you three choices: **INSTALL**, **RUN PROGRAM**, and **FINDER**.
  - Click on **INSTALL** to complete the installation procedure. When this is done, the program itself will start.
  - Click on **RUN PROGRAM** to run **Crossword Magic** without installing it.
  - Click on **FINDER** to end the installation process and return to the **Finder**.

5. If you copy **Crossword Magic** to your hard drive without completing the installation procedure, you will be prompted to insert your original program disk each time you attempt to run the program from your hard drive.
6. You may not install **Crossword Magic** to another hard drive until you have uninstalled it from the first.
7. To save space on your hard drive, you may wish to delete the **System** folder from the newly created **CM Disk** folder. Do **NOT** delete your hard drive's **System** folder or the **System** folder from your **Crossword Magic** program disk.

## Uninstalling Crossword Magic from a Hard Drive

To uninstall **Crossword Magic** from your hard drive:

1. Insert the **Crossword Magic** disk into any floppy drive. Double-click on the disk icon to open it, if necessary; then double-click on the **Crossword Magic** program icon (on the program disk, not on the hard drive).
2. A dialog box will appear. It will tell you how many hard disk installs remain on the disk (it should be 0) and give you three choices: **REMOVE**, **RUN PROGRAM**, and **FINDER**.
  - Click on **REMOVE** to remove the install from your hard drive.
  - Click on **RUN PROGRAM** to run **Crossword Magic** without uninstalling it.
  - Click on **FINDER** to end the uninstallation process and return to the **Finder**.
3. Once you have uninstalled **Crossword Magic** from your hard drive, the program files will remain, but you won't be able to run the program from the hard drive without inserting the program disk itself. However, you may now install the program onto another hard drive or run the program from the floppy.

**Note:** Before backing up your hard drive, it is a good idea to uninstall **Crossword Magic** from your hard drive.

Program Copyright © 1990, 1987 L&S Computerware. All rights reserved. Documentation copyright © 1990 Mindscape Inc. All rights reserved. Crossword Magic is a trademark of L&S Computerware. Macintosh, LaserWriter, and ImageWriter are registered trademarks of Apple Computer, Inc.



Mindscape Inc. • A Software Toolworks Company  
60 Leveroni Court  
Novato, CA 94949

02318R