



Smart 340(L)
Software
Version 1.4.2
Official Release

Scitex Corporation Ltd., Herzlia, Israel

Date: September 26, 1997

To: Distribution

From: Ronny Cohen

SUBJECT: Smart 340(L) Software Version 1.4.2 Official Release.

Distribution

STIL: E. Shalev, A. Shorr, H. Melman, G. Shamri, S. G aribi
M. Yanai, G. Benyamini, M. Keydar, S. Pekar, A. Shvarts,
A. Schori, A. Warshavsky, I. Carmi

ICS: S. Kedem

STA: B. Poberezky, S. Shemesh, Z. Argov, Aron Blum,
A. Basanchik

STE: H. Ben-Shabat, S. Cohen, M. Tidmus, F. Haesebeyt,
M. Sitton, C. Gijbels

STN: T. Aoki, H. Sekido, S. Takada, Y. Nakao, K. Hiraoka, O. Peer

STAP: A. Lombrozo, M. Ditchett, C. Callebaut, D. Sakai

STMA: Y. Suffrin, A. Elazar, Z. Hovav

IMPORTANT NOTICE

This document is delivered subject to the following conditions and restrictions:

This document contains proprietary information of Scitex Corporation Ltd.

Such information is hereby supplied solely for the purpose of assisting explicitly and properly authorized users of Scitex products. Without the express prior written permission of Scitex, no part of the contents hereof may be used for any other purpose, disclosed to any person or firm, or reproduced by any means.

The text and drawings herein are for the purposes of illustration and reference only.

The specifications on which they are based are subject to change without notice.

Scitex and the Scitex logo are trademarks of Scitex Corporation Ltd. and may be registered in certain jurisdictions.

Document Number 771-51126A

Catalog Number 399Z51126A

Copyright © 1997 by

Scitex Corporation Ltd.

All Rights Reserved

September 1997

SMART 340(L) VERSION 1.4.2 OFFICIAL RELEASE

Enclosed please find the official release document of the *Smart 340(L) Software Version 1.4.2* (Software version catalog no. **501V37366M**).

This document is an overview of the main changes from software version 1.4.1, including system requirements and software loading procedure.

Detailed descriptions of the Smart 340(L) appear in the *Smart 340/Smart 340L User Guide*, Catalog No. 399Z1G333 and the *Smart 340(L) Update to Version 1.3*, Catalog No. 399Q5H036.

Changes from version 1.4.1 to version 1.4.2

Compatibility with Mac OS 8.0

System Requirements

Operating the **Smart 340(L)** requires a Macintosh Quadra or higher, including Power Macintosh with the following:

- ◆ 16 MB of available memory (RAM) for the scanning application, not including the memory needed for the system software.
- ◆ Hard disk. Its capacity depends on your needs, such as picture size. At least 250 MB is recommended.
- ◆ Color monitor with a display capability of millions of colors. The application is designed for 19" monitors, but can operate with 16" and 17" monitors.
- ◆ Macintosh system version 7.1.2 or higher.

Software Installation

This section describes the **Easy Install** method used for installing the software. The **Smart 340(L) software version 1.4.2** is contained in six diskettes. These are 3.5" high-density diskettes in compressed format.

- ◆ Insert the diskette labeled **Smart 340(L) 1 of 6**.
- ◆ Double click on the **Smart 340(L) S/W Installer** icon. The *Scitex Installer* screen appears.
- ◆ Click **Continue**. A readme file opens.
- ◆ Click **Continue**. The *Smart 340(L) S/W Installer* window appears.

The **Install Location** section of the window shows where, by default, the **Smart 340(L)** folder will be located. You can change this location. The procedure to be used depends on whether you have one hard disk, or more than one.

One hard disk

- ◆ Click **Select Folder**. In the directory dialog box that appears, select the new location and click **Select** to return to the *Smart 340(L) S/W Installer* window.

More than one hard disk

- ◆ Click **Switch Disk** to change the disk. When the name of the requested disk appears, set the location of the **Smart 340(L)** folder. To do so, press the indicator and choose **Select Folder**. In the directory dialog box that appears, select the new location and click **Select** to return to the *Smart 340(L) S/W Installer* window.
- ◆ In the *Smart 340(L) S/W Installer* window, click **Install**.

The installation program continues automatically from this stage on.

During installation, a progress bar keeps you informed of the installation stage.

A message appears each time you are requested to insert one of the diskettes. When the installation program is completed, a message appears. Click **Quit** to exit the Installer.

□ If your computer does not have the Gamma control panel, then during installation, it is installed on your computer. A setting table is also installed. The Gamma control panel and setting table are used by the **MatchBuilder** application, which is also included in this version (see next page).

The software is now installed. The **Smart 340(L) 1.4.2** folder contains the following:

Smart340(L) 1.4.2	Smart 340(L) scanning application for Smart 340/Smart 340L scanners.
Smart340(L) Install & Utils 1.4.2	For scanner installation and automatic creation of tables.
Smart340(L) Calibration 1.4.2	Intended for service engineers only.
MatchBuilder 1.0.0	This folder contains the <i>MatchBuilder</i> application and a readme file describing the application and how to use it (in <i>Microsoft Word</i>).
Scitex SCSI Information	Shows the devices connected to the SCSI bus. Needed when connecting the scanner to the Macintosh.
Smart340(L) Diag 1.4.2	Display and test the status of all scanner hardware functions.
Scitex Tables	Scitex-supplied tables.